

Variables

- **DEPENDS** Lists a recipe's build-time dependencies. These are dependencies on other recipes whose contents (e.g. headers and shared libraries) are needed by the recipe at build time.
- **RDEPENDS** Lists runtime dependencies of a package. These dependencies are other packages that must be installed in order for the package to function correctly.
- **PN** - The recipe name
- **PR** - The recipe revision
- **PV** - The recipe version

Build related:

- **S** (by default `${WORKDIR}/${BPN}-${PV}`) - directory within build directory, where unpacked recipe source code resides.
- **B** (by default the same as **S**) - directory within build directory, where objects are generated.
- **D** - directory within build directory, where components are installed (destination directory)

Variable name	Definition	Typical value
prefix	/usr	/usr
base_prefix	(empty)	(empty)
exec_prefix	<code>\${base_prefix}</code>	(empty)
base_bindir	<code>\${base_prefix}/bin</code>	/bin
base_sbindir	<code>\${base_prefix}/sbin</code>	/sbin
base_libdir	<code>\${base_prefix}/lib</code>	/lib
datadir	<code>\${prefix}/share</code>	/usr/share
sysconfdir	/etc	/etc
localstatedir	/var	/var
infodir	<code>\${datadir}/info</code>	/usr/share/info
mandir	<code>\${datadir}/man</code>	/usr/share/man
docdir	<code>\${datadir}/doc</code>	/usr/share/doc
servicedir	/srv	/srv
bindir	<code>\${exec_prefix}/bin</code>	/usr/bin
sbin	<code>\${exec_prefix}/sbin</code>	/usr/sbin
libexecdir	<code>\${exec_prefix}/libexec</code>	/usr/libexec
libdir	<code>\${exec_prefix}/lib</code>	/usr/lib
includedir	<code>\${exec_prefix}/include</code>	/usr/include
palmtopdir	<code>\${libdir}/opie</code>	/usr/lib/opie
palmqtdir	<code>\${palmtopdir}</code>	/usr/lib/opie

From:

<https://niziak.spox.org/wiki/> - **niziak.spox.org**

Permanent link:

<https://niziak.spox.org/wiki/sw:yocto:bitbake:vars>

Last update: **2022/10/25 13:35**

